How to create the YouTube API?

- ➤ Go to https://console.cloud.google.com/
- Sign into your Google Account
- Create Project
- ➤ Go to Library -> select the required YouTube API from the list (we are using YouTube Data API v3)
- > Enable API
- Create API key -> select Credentials > Create Credentials > API Key

YouTube Documentation:

https://developers.google.com/youtube/v3

Prerequisites:


Python 2.7 or Python 3.5+

The pip package management tool

The Google APIs Client Library for Python:


pip install --upgrade google-api-python-client

- Execute the Python script youtube_etl.py to extract the YouTube data.
- > Create EC2 instant that is the online machine and deploy Airflow on that.
 - Login to AWS account
 - Select EC2 > Instances > Launch Instances > provide Name and tags (e.g. airflow_project)
 - Choose Application and OS Image → Ubuntu
 - Choose Instance Type → t3_medium (additional charge required, else go with t2_micro it is free)
 - Create key-pair to access the EC2 instance: airflow_ec2_key →key will be downloaded → keep the key in the same folder
 - Allow SSH, HTTP, HTTPS traffic from internet
 - Launch Instance



Connect to Airflow:

- Select the Instance > Click on 'Connect' > SSH client > copy the autogenerated example



Open cmd and past the key, make sure to be in the same folder

```
C:\Users\amrit\OneDrive\Documents\GitHub\YouTube_Data_Pipieline_Using_Airflow>ssh -i "airflow_ec2_key.pem" ubuntu@ec2-13-52-254-93.u-west-1.compute.amazonaws.com
The authenticity of host 'ec2-13-52-254-93.us-west-1.compute.amazonaws.com (13.52.254.93)' can't be established.
ED25519 key fingerprint is SHA256:nUr60Zefl7Y8TFaWkgAsIaWy7yDioCMENgXTM4bYGOc.
This key is not known by any other names
Are you sure you want to continue connecting (yes/no/[fingerprint])? yes
Warning: Permanently added 'ec2-13-52-254-93.us-west-1.compute.amazonaws.com' (ED25519) to the list of known hosts.
Connection closed by 13.52.254.93 port 22
C:\Users\amrit\OneDrive\Documents\GitHub\YouTube_Data_Pipieline_Using_Airflow>
```

Ubuntu console will open: (run command twice if the ubuntu console is not up the first time)

```
* Support: https://ubuntu.com/advantage

System information as of Thu Oct 12 05:52:09 UTC 2023

System load: 0.0 Processes: 96
Usage of /: 20.6% of 7.57GB Users logged in: 0
Memory usage: 23% IPv4 address for eth0: 172.31.11.17

Swap usage: 0%

Expanded Security Maintenance for Applications is not enabled.

0 updates can be applied immediately.

Enable ESM Apps to receive additional future security updates.

See https://ubuntu.com/esm or run: sudo pro status

The list of available updates is more than a week old.

To check for new updates run: sudo apt update

The programs included with the Ubuntu system are free software; the exact distribution terms for each program are described in the individual files in /usr/share/doc/*/copyright.

Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by applicable law.

To run a command as administrator (user "root"), use "sudo <command>". See "man sudo_root" for details.

ubuntu@ip-172-31-11-17:-$
```

Install the following SSH commands in the ubuntu console:
sudo apt-get update
sudo apt install python3-pip
sudo pip install apache-airflow
sudo pip install pandas
sudo pip install s3fs
sudo pip install tweepy→ for twitter data
sudo pip install --upgrade google-api-python-client → for YouTube

- Check if everything is installed properly write 'airflow' in the ubuntu console:

```
ubuntu@ip-172-31-11-17: ~
                                   X
ubuntu@ip-172-31-11-17:~$ airflow
Usage: airflow [-h] GROUP_OR_COMMAND ...
Positional Arguments:
 GROUP_OR_COMMAND
   Groups:
     config
                    View configuration
                   Manage connections
                   Manage DAGs
     dags
                    Database operations
                   Manage jobs
     jobs
     pools
                    Manage pools
     providers
                   Display providers
                    Manage roles
                    Manage tasks
     users
                    Manage users
     variables
                    Manage variables
   Commands:
     cheat-sheet
                    Display cheat sheet
     dag-processor Start a standalone Dag Processor instance
                    Show information about current Airflow and environment
     kerberos
                    Start a kerberos ticket renewer
                    Dump information about loaded plugins
     plugins
                    Rotate encrypted connection credentials and variables
     scheduler
                    Start a scheduler instance
     standalone
                   Run an all-in-one copy of Airflow
                  Update permissions for existing roles and optionally DAGs
     sync-perm
                    Start a triggerer instance
     triggerer
                    Show the version
     version
                    Start a Airflow webserver instance
Options:
 -h, --help
                    show this help message and exit
airflow command error: the following arguments are required: GROUP_OR_COMMAND, see help above.
ubuntu@ip-172-31-11-17:~$
```

- Connect to the airflow server: airflow standalone
- ➤ Create a 'youTube dag.py' file (refer file for the code) → import the ETL function from 'youTube etl.py' file
- Create a S3 bucket (<u>S3 buckets | S3 | Global (amazon.com)</u>)

ubuntu@ip-172-31-3-89:~/airflow\$ sudo nano airflow.cgf


Save the file we created in the S3 bucket in the 'youTube_etl.py' file e.g., channel_stat.to_csv('s3://amrita-neogi-yt-bucket/youtube_stat.csv')

```
Connect to the airflow again → make changes to 'airflow.cfg'
ubuntu@ip-172-31-3-89:-$
ubuntu@ip-172-31-3-89:-$
ubuntu@ip-172-31-3-89:-$
ubuntu@ip-172-31-3-89:-$
ubuntu@ip-172-31-3-89:-$
ubuntu@ip-172-31-3-89:-$ cd airflow/
ubuntu@ip-172-31-3-89:-\airflow$ 1s
airflow-webserver.pid airflow.cfg airflow.db logs standalone_admin_password.txt webserver_config.py
```


```
[core]
# The folder where your airflow pipelines live, most likely a
# subfolder in a code repository. This path must be absolute.
dags_folder = /home/ubuntu/airflow/dags
# Hostname by providing a path to a callable, which will resolve the hostname.
# The format is "package.function".
#
```

Change 'dags' to 'youTube_dag' or anyother preferred name


- > Create a new folder inside S3 copy the etl.py code from local folder to the EC2 machine
 - mkdir youTube dag
 - cd youTube dag
 - sudo nano youTube dag.py
 - copy code from 'youTube dag.py' and paste here
 - ctrl + X to save the file
 - repeate same process for etl file sudo nano youTube_etl.py copy code from 'youTube_etl.py' and paste here ctrl + X to save the file
- ** to stop airflow server \rightarrow ctrl + C
 - Make sure to have permission from the EC2 to write on the S3 bucket.



Create IAM role



Give S3 and EC2 full access:



- ✓
 Image: AmazonEC2FullAccess
 AWS managed

 ✓
 Image: AmazonEC2ReadOnlyAccess
 AWS managed

 ✓
 Image: AmazonEC2RoleforAWSCodeDeploy
 AWS managed
- Create role 's3_ec2_airflow_role'
- Update IAM role

